

Pivariety Low Light Camera Module for Raspberry Pi



2MP IMX462 (SKU: B0333)

QUICK START GUIDE

SPECS

Image Sensor	2MP IMX462
Max. Resolution	1920H×1080V
Pixel Size	2.9um x 2.9um
Optical Format	1/2.8"
Lens Spec	Mount: M16
	Focal length: 4mm±5%
	F.NO: 0.95±5%
	FOV: 92.23deg (H)
Minimum Illumination	0.01Lux
IR Sensitivity	Integral IR filter, visible light only
Frame Rate	Adjustable, 5-60fps@1080P
Sensor Output Format	RAW10
ISP Output Format	Output image format of JPG, YUV420, RAW, DNG; output video format of MJPEG, H.264
Interface Type	2-Lane MIPI
Board Size	38mm×38mm

View the Status of Driver and Camera

dmesg | grep arducam

It will display arducam-pivariety if driver installed successfully and firmware version if the camera can be detected. The display should be probe failed if the camera can't be detected, you might have to check the ribbon connection, then reboot the Raspberry Pi.

View the Video Node

The Pivariety camera modules are emulated as the standard video device under /dev/video* node, so you can use the Is command for listing the contents in the /dev folder.

Is /dev/video* -I

Since the camera module is V4L2 compliant, you can use the V4I2 controls to list the supported color space, resolutions, and frame rates.

v4l2-ctl --list-formats-ext

NOTE: Although V4L2 interface is supported, only RAW format images can be obtained, without ISP support,

3. Official Libcamera App Installation

. /install_pivariety_pkgs.sh -p libcamera_dev . /install pivariety pkgs.sh -p libcamera apps

4. Capture Image and Record Video

TROUBLESHOOT

1. Cannot Allocate Memory

[3:45:35.833744413] [6019] INFO RPI raspberrypi.cpp:611 Sensor: / base/soc/i2c0mux/i2c@1/arducam@0c – Selected mode: 5344×4012-pRAA

[3:45:35.948442507] [6019] ERROR V4L2 v4l2_videodevice.cpp:1126/dev/video14[17:cap]: Unable to request 4 buffers: Cannot allocate memory $[3:\!45:\!35.948551358]$ [6019] ERROR RPI raspberrypi.cpp:808 Failed to allocate buffers

ERROR: *** failed to start camera ***

Edit /boot/cmdline.txt and add cma=400M at the end

2. The Image Displays Color Dots

Add code --denoise cdn off at the end of command

./libcamera-still -t 5000 -o test.jpg --denoise cdn off

More details: https://github.com/raspberrypi/libcameraapps/issues/19

3. Failed to Install the Driver

The Pivariety V4L2 kernel driver only supports the 5.10 version of Raspberry Pi OS. You can follow Arducam Doc page to build the drivers for other kernel versions.

4. Failed to import fd 18

If you find the same error, you may make the wrong selection about the graphics driver. Please follow Arducam Doc page to select the correct graphics driver

INTRODUCTION

About Arducam

Arducam has been a professional designer and manufacturer of SPI, MIPI, DVP and USB cameras since 2012. We also offer customized turnkey design and manufacturing solution services for customers who want their products to be unique.

About Pivariety Camera

Arducam Pivariety is a Raspberry Pi camera solution to take the advantage of using its hardware ISP functions. Using Arducam Pivariety camera modules, users can get better performance and a wider variety of camera, lens options. For a long time, Raspberry Pi users are limited to use the closed-source official supported camera driver and camera modules (V1/V2/HQ).

Now Arducam made it possible to provide welltuned ISP for Pivariety camera modules with Auto Exposure, Auto White Balance, Auto Gain Control, Lens Shading Correction, etc. This series of cameras use the libcamera framework, they can't be supported by Raspistill, and the way to access the camera is libcamera SDK(for C++)/libcamera-still/ libcamera-vid/Gstreamer.

If you want to know more about other models of Pivariety Camera, please visit: https:// www.arducam.com/docs/cameras-for-raspberrypi/pivariety/

SOFTWARE

1. Driver Installation

wget -O install pivariety pkgs.sh https://github.com/ ArduCAM/Arducam-Pivariety-V4L2-Driver/releases/ download/install script/install pivariety pkgs.sh

chmod +x install pivariety pkgs.sh

. /install pivariety pkgs.sh -p kernel driver

press y to reboot

NOTE: The kernel driver installation only supported by the latest version 5.10. For other kernel versions, please go to our Doc page: https:// www.arducam.com/docs/cameras-for-raspberrypi/pivariety/how-to-install-kernel-driver-forpivariety-camera/#2-how-to-build-raspberry-pikernel-driver-for-arducam-pivariety-camera

You can also visit this doc page to refer to the hardware connection: https:// www.arducam.com/docs/cameras-for-raspberrypi/pivariety/2mp-imx462-pivariety-low-lightcamera-module/

2. Test the Driver and Camera

After you've finished the hardware assembly and driver installation, you can test whether the camera is detected and working.

Capture image

For example, preview for 5s and save the image named

cd libcamera-apps/build

./libcamera-still -t 5000 -o test.jpg

Record video

For example, record a H.264 10s video with the frame size 1920W × 1080H

cd libcamera-apps/build

./libcamera-vid -t 10000 --width 1920 --height 1080 -o

 Plugin gstreamer installation Install gstreamer

sudo apt update

sudo apt install -y gstreamer1.0-tools

Preview

cd ~/libcamera

export GST PLUGIN PATH=\$(pwd)/build/src/gstreamer

gst-launch-1.0 libcamerasrc! 'video/xraw,width=1920,height=1080' ! videoconvert ! autovideosink

5. Switch to the native camera (raspistill etc.)

Edit the file of /boot/config.txt, make dtoverlay=arducam change to # dtoverlay=arducam

After the modification is completed, you need to reboot the Raspberry Pi.

cd libcamera-apps/build

CONTACT US

1. More about Pivariety Camera

If you want to know more about other models of Pivariety Camera, please visit: https://www.arducam.com/docs/ cameras-for-raspberry-pi/pivariety/

2. About Customer Service

If you need our help or want to customize other models of Pi cameras, feel free to contact us.

Email: support@arducam.com Website: www.arducam.com

Skype: Arducam